


SAMPLE	KEY/SKU	QTY	CUT
	A Empire Star 2550-88 Blue/Brown Panel	24"	(1) Cut panel to measure 22 1/2" square. (4) 6 1/2" square for corners.
	B Tribeca 2556-72 Brown	1 YD	(4) 5 1/2" squares for center corners. (5) 4" x WOF strips, outer border must be pieced.
	C Rush Hour 2555-33 Gold	1/2 YD	(4) 1 1/2" x WOF. (4) 2 1/2" x WOF.
	D Link on Center 2554-72 Rust	1/4 YD	(8) 3 1/2" x 6 1/2" rectangles.
	E Hudson River 2553-72 Brown	1/4 YD	(8) 3 1/2" x 6 1/2" rectangles.
	F Hudson River 2553-13 Gray	1/4 YD	(8) 3 1/2" x 6 1/2" rectangles.
	G Link on Center 2554-55 Blue/Brown	1/4 YD	(8) 3 1/2" x 6 1/2" rectangles.
	H Tribeca 2556-11 Red	1/3 YD	(4) 2 1/2" x WOF.

*WOF=Width of Fabric

QUILT ASSEMBLY


Begin by making center block, shown in diagrams below.





1. Take (4) 5 1/2" squares **B** and either fold diagonally and press with iron or draw a diagonal line on wrong side. Place one square **B** on upper left hand corner of center square **A**, right sides together. Sew on diagonal line. Flip the lower right hand corner to upper left hand corner. Press. Trim excess fabric on reverse side to 1/4" as shown on middle diagram. Repeat steps for the remaining (3) squares to complete center block. Set aside.

2. Add 1 1/2" strips **C** to sides of center square, trim to fit. Then add to top and bottom, trim to fit..

3. Following photo and diagrams below, sew sets of **D-E** and **F-G** rectangles together. Then sew two **D-E** units to two **F-G** units in alternating ways, follow photo for color placement. Take (2) **D-E-F-G** units and sew to sides of quilt center.



4. Next attach corner medallions **A** to ends of (2) remaining **D-E-F-G** units, as shown on left diagram. Sew the latter to the top and bottom of quilt center.




BORDER ASSEMBLY

5. Add 2 1/2" of the **C** spacer strip to sides of quilt center. Then add **C** strips to top and bottom.

6. Next add **H** strips first to sides and repeat for top and bottom of quilt center. You may have to sew extra fabric to top and bottom strips. Use the left over pieces from side strips. See steps below for adding pieces.

7. Final border **B** must be pieced. **FOR SIDES:** Measure quilt center to determine the size of strip you will need (should be about 44 1/2"). For the extra inches you need to add, cut a strip and divide it in two to add to ends of a 4" x WOF strip. See diagrams in bottom left. Don't forget to add 1/2" for seam allowances. **FOR TOP AND BOTTOM:** Repeat side border steps above (should be about 51 1/2"). See diagrams on left.



Finished quilt size: 51" square

FINISHING Cut batting and backing 3" larger than top on all sides. Assemble the quilt sandwich by placing the backing, batting and top together in layers and baste or pin with safety pins. Machine quilt as desired. When quilting is completed, trim excess batting and backing. Bind in the usual manner.