


SAMPLE	Kŀ	EY/SKU	QTY	CUT	CUT PIECES VIA WOF
	A	Locomotion Panel 2694-55 <i>Blue</i>	1 Panel (24")	Trim to	23" x 32-1/2".
	в	Locomotion Texture 2700-05 <i>Blue</i>	5/8 YD	SUBCI TOP L (2) 3-3/ SUBCI TOP R (4) 6' sc	8" x 10-1/2" rectangle, ut once diagonally from eft to bottom right (B1). 8" x 10-1/2" rectangle, ut once diagonally from right to bottom left (B2). uates. 4" squares.
	С	Crawford Notch 2692-10 <i>Red</i>	3/8 YD		4" x 23" strips. 4" x 32-1/2" strips.
	D	Crawford Notch 2692-07 <i>Natural</i>	3/8 YD		4-1/2" rectangles. 6" rectangles.
	E	Fast Track 2698-55 <i>Blue</i>	5/8 YD		x 6" LOF rectangles. NGLE TEMPLATE (CUT VIA WOF).
	F	Ride the Rails 2695-77 <i>Antique</i>	1/4 YD	(4) 6" so	juares.
	G	Locomotion Texture 2700-10 <i>Red</i>	3/8 YD	(5) 2-1/	4" x WOF strips*
	H	Stationmaster 2699-77 Antique	1-1/2 YD	FROM REM	: 2" x LOF strips. MAINDER OF FABRIC CUT 2" x WOF strip*.
*CEW CTDIDE 1	I	Locomotion Texture 2700-79 <i>Brown</i>	1/2 YD		4" x WOF strips; BINDING.

*sew strips via short ends, then gq' to bg der assembly | wof/lof=width/length of farric



BLOCK ASSEMBLY See QUILT DIAGRAM for steps below.

1. Sew (1) C 2-1/4" x 32-1/2" strips to each side of A 23" x 32-1/2" panel. Set aside.


2. BC STRIP: Sew (1) **B** 2-1/4" square to each end of (1) C 2-1/4" x 23" strip. Make 2 BC strips. Sew one BC strip to top and one to bottom of AC PANEL. Set aside.

3. PIECED SIDE BORDER: Sew pieces as follows: (2) **B** 6" squares | (2) **D** 4" x 6" rectangles. (1) E 18" x 6" rectangles (LOF)

E D B B D

Trim to 6" x 36". Make 2 PIECED SIDE BORDERS and sew one to each side of panel unit. Set aside.

4. EB UNIT: Sew (1) B1 and (1) B2 TRIANGLE to each side of (1) E TRIANGLE TEMPLATE. Trim to 6" x 9-1/2". Make 4 EB UNITS. Then sew (2) EB units together as shown in diagram below. Trim to 6" x 18-1/2".



MAKE 2 EB UNIT PAIRS

5. PIECED TOP/BOTTOM BORDER: Sew pieces as follows: (2) **EB** UNITS (2) **D** 6" x 4-1/2" rectangles (2) **F** 6" squares



Trim to 6" x 37". Make 2 PIECED BORDERS and sew one to top and one to bottom of panel unit. Set aside.

BORDER ASSEMBLY *Measure width and length of quilt* top to ensure **G** and **H** border cutting sizes. Below are our measurements.

6. G/BG SASHING BORDER: Sew (1) G 2-1/2" x (47") strip to each/side of quilt top. Add (1) B 2-1/4" square to each end of (1) G 2-1/4" x (37-1/2") strip. Make 2 BG strips and sew one to top and one to bottom of quilt top.

7. H BORDER: Sew (1) H 5-1/2" x (51") strip to each side of quilt top. Then sew (1) H 5-1/2" x (52") strip to top and to bottom of quilt top.

FINISHING Cut batting and backing 3" larger than top on all sides. Layer backing, batting and top together and baste or pin. When guilting is completed, trim excess batting and backing. Bind as usual.

FINISHED SIZE: 50-1/2" x 60".

Note: If this Behartex pattern is included in a kit, any questions about the kit should be addressed to the vendor from whom you bought it.

BENARTEX, LLC

132 WEST 36TH STREET,\4TH FL. • NEW YORK, NY 10018 212-840-3250 · WWW.BENARTEX.COM

TRIANGLE TEMPLATE: 6-1/4" W X 9-3/4" L