


^{*}SEW STRIPS VIA SHORT ENDS THEN GO TO BORDER ASSEMBLY | WOF=WIDTH OF FABRIC PLUM COLORWAY
TURQUOISE COLORWAY
BOTH COLORWAYS

UNIT ASSEMBLY

8 **BD** units, NOTE B SQUARE GOES TO BOTTOM LEFT CORNER OF D STRIP. Set Aside. C corner. Trim excess fabric on reverse side to 1/4". Make 8 BC units and ${\bf C}$ 2-1/2" x 8-1/2" strip and sew on diagonal line. Press ${\bf B}$ open towards wrong side. Place B square right sides together at bottom right corner of 1. BC/BD Unit: Take (1) B 2-1/2" square and draw a diagonal line on the



UNIT ONE: TRIM TO 2-1/2" x 16-1/2" 2. Sew following pieces, as shown in diagrams, to make Units One-Seven MAKE 8 **UNIT TWO:** TRIM TO 2-1/2" x 16-1/2"

(2) **B** 1-1/2" x 2-1/2" strips (1) **E** 2-1/2" square

(1) **C** 2-1/2" x 6-1/2" strip

OF EACH TINU

W

(1) **D** 2-1/2" x 6-1/2" strip

(1) **E** 2-1/2" x 4-1/2" strip (1) **D** 2-1/2" x 5-1/2" strip (1) **C** 2-1/2" x 5-1/2" strip (2) **B** 1-1/2" x 2-1/2" strips

Tu

UNIT THREE: TRIM TO 2-1/2" x 24-1/2"

SAMPLE KEY/SKU

CUT

- (2) **B** 1-1/2" x 2-1/2" strips (1) **E** 2-1/2" x 6-1/2" strip
- (1) C 2-1/2" x 8-1/2" strip
- (1) **D** 2-1/2" x 8-1/2" strip
- w D



UNIT SIX: TRIM TO 2-1/2" x 8-1/2" (2) **B** 2-1/2" x 1-1/2" strips (1) **E** 2-1/2" x 6-1/2" strip

В

9 S 1 \triangleright

UNIT FOUR: TRIM TO 2-1/2" x 8-1/2"

UNIT FIVE: TRIM TO 2-1/2" x 8-1/2"

- (1) **E** 2-1/2" square (2) **B** 1-1/2" x 2-1/2" strips
- (1) **D** 2-1/2" square (1) **C** 2-1/2" square
- В ...

(1) **D** 2-1/2" x 4-1/2" strip (1) C 2-1/2" x 1-1/2" strip (2) **B** 2-1/2" x 1-1/2" strips (1) **E** 2-1/2" x 4-1/2" strip

UNIT SEVEN: TRIM TO 2-1/2" x 24-1/2"

(1) **BC** unit and (1) **BD** unit

(1) **E** 2-1/2" x 8-1/2" 7

BC UNIT

BLOCK/QUILT ASSEMBLY REFER TO QUILT DIAGRAM FOR STEPS BELOW.

x 8-1/2" strips make Block as shown in Block Diagram. Square to 24-1/2". Make 4 Blocks. Then sew blocks together. See Quilt Diagram **3.** Using Units 1-7, **A** 4-1/2" squares, **A** 8-1/2" squares and **E** 2-1/2"


4. Sew B and E borders to quilt top. For each border begin with BORDER ASSEMBLY Measure width and length of quilt top to ensure **B** and **E** border sizes. Below are our measurements

BORDER 1: E 2-1/2" x (48-1/2") SIDES. E 2-1/2" x (52-1/2") TOP/BOT sides first, then proceed to top and bottom.

FINISHING Cut batting and backing 3" larger than top on all sides. Layer backing, batting and top BORDER 2: B 2-1/2" x (52-1/2") SIDES. B 2-1/2" x (56-1/2") TOP/BOT. BORDER 3: E 2-1/2" x (56-1/2") SIDES. E 2-1/2" x (60-1/2") TOP/BOT.

together in layers and baste or pin. After quilting, trim excess batting and backing. Bind as usual

Quilt Diagram



UNIT/BLOCK DIAGRAM FOR TURQUOISE COLORWAY

C			Α		SEE QUILT PHOTO TO MAKE QUILT TOP AND BORDERS
В	C	C			T PI
_	B		С	С	OTO
		₩			TO
			В	₩	MA
	ET.	ΙĦ	H	BEB	KE
				ᄧ	QUII
		W	В		T T
	B		D	D	'OP'
					AND
	D	D			ВО
L			;	>	RDE
					RS



ᄧᄧ

