5. Use a pin or two to hold the mitered corner in place. From the underside, stitch in the pressed crease. Check to see that it's correct and if it is, trim the excess from the seam to 1/4". Press these seams open. Repeat Steps 4-5 for each of the corners to be mitered.




6. Layer your quilt and prepare to quilt your masterpiece. Outline the block parts, plus outline the shapes in the Border and blocks.

7. Bind with the **A** fabric, following the instructions with the Binding Miter Tool. There is also a video demo of this terrific tool on *www.youtube.com*

FINISHING: Cut batting and backing 3" larger than top on all sides. Layer backing, batting and top together and baste or pin. When quilting is completed, trim excess batting and backing. Bind as usual.

Finished Quilt Size 55" x 66"



Share your finished quilt with the Benartex community on social media by tagging #benartex_fabrics!



Note: If this Benartex pattern is included in a kit, any questions about the kit should be addressed to the vendor from whom you bought it.

BENARTEX, LLC • 132 WEST 36TH STREET, 4TH FLOOR NEW YORK, NY 10018 • T: 212-840-3250 • WWW.BENARTEX.COM



SAMPLE		KEY/SKU	QTY	СИТ
	А	Snowflake Stripe 2656M-42 Green/Cream	3-7/8 yds	Cut (5) Vertical 4-1/2" stripes, all matching into: (2) 4-1/2" x 72" (2) 4-1/2" x 56" (82) 4-1/2" squares Cut (2) 2-1/2" x LOF from the scraps for Binding
	В	Snow Fall Swirl 2655M-12 <i>Black</i>	5/8 yd	Cut (4) 4-1/2" strips into: (33) 4-1/2" squares
	С	Snow Fall Swirl 2655M-10 <i>Red</i>	5/8 yd	Cut (4) 4-1/2″ strips into: (32) 4-1/2″ squares
	D	Metallic Snowflake 2650M-07 Cream	3/8 yd	Cut (2) 4-1/2" strips into: (18) 4-1/2" squares


LOF = LEGNTH OF FABRIC | *SEW STRIPS VIA SHORT ENDS

QUILT ASSEMBLY

1. Use all the 4-1/2" squares to lay out the quilt. Notice the **A** fabric is vertical on alternating rows and horizontal on the others. Also notice the vertical rows alternate with the Green on the right or on the left. Likewise the horizontal rows alternate having the Green on the bottom or on the top.

2. Stitch the quilt top together following the diagram on the following page. Press carefully.

3. Attach the borders. Begin and end at the 1/4" seam allowance at each corner, and leave a 5" miter 'tail' extending.



BORDER ASSEMBLY

4. Place a corner to miter on your ironing board, with the border that is lying horizontal extending to the right, and the one that is vertical on top of it and extending up. Fold the top extending border diagonally under and position so it is exactly on top of the one extending to the right. Once you are satisfied that the miter is correct, smash it with the iron.

